

Installing CheckSum Test System Software on a Windows 7(32-bit) PC

On some Windows 7 PCs, the installation of the CheckSum Test System software requires a new folder to be created.

Using the CheckSum DVD

- Place the DVD in the PC
- The DVD may autorun (if enabled) otherwise open the DVD drive directory and double click **start (start.html)**
- Click to **Install Test System Software**
- Select the CheckSum version of software for your Windows 7 PC
- Run the **setup.exe** file software installation

Using the CheckSum Software Download Web Site

- Open the folder with the CheckSum version of software for your Windows 7 PC
- Download and open the zip file
- Run the **setup.exe** file software installation

Installation Begins

Window opens and warns: **The Publisher could not be verified. Are you sure you want to run this software?**

Click: **Run**

If an **Unable to save file** message appears then

Click: **Open**

Window opens: **Browse for folder**

Leave this window temporarily until you finish the next few steps


Create Folder

Open **Windows Explorer**

- Select C:
- Create a New folder and name the New folder **CheckSum**

Installing CheckSum Test System Software on a Windows 7(32-bit) PC

The Windows Explorer should be as shown:



You can close Windows Explorer

Continue the Installation

Open the window with: **Browse for folder**

Browse to: **C:\Checksum**

Select: **OK**

Checksum software will now continue to install

Click **Next**

Select: **I accept the terms in this license agreement – Next**

Select the destination folder: **C:\Checksum – Next**

Install the application for:

Select: **Anyone who uses this computer (All users)**

User Account Control window opens with: **Do you want to allow the following program from an unknown publisher to make changes to this computer?**

Click **Yes**

At the message: **Windows can't verify the publisher of this driver software**

Select: **Install this driver software anyway**

Window opens regarding the CheckSum USB module:

Please attach your device to this computer anytime after the installation has finished

Select: **OK**

Select: **Finished**

Installing CheckSum Test System Software on a Windows 7(32-bit) PC

Adding Support for WinHLP files

Later versions of Windows do not directly support the .HLP file format used by the CheckSum software. You must download a free patch file from the Microsoft web site. <http://www.microsoft.com/en-us/download/details.aspx?id=91>

Download and install the -x86 version(32 bit):

Choose the download you want

<input type="checkbox"/> File Name	Size
<input checked="" type="checkbox"/> Windows6.1-KB917607-x86.msu	688 KB
<input type="checkbox"/> Windows6.1-KB917607-x64.msu	702 KB

After the patch is installed you will be able to view the CheckSum Help files.